


www.firstcoastcardio.com | 904.493.3333



OEIS 6TH ANNUAL NATIONAL SCIENTIFIC MEETING

April 4-6, 2019 St. Petersburg, Florida





Complications Defined

- Access Complications
 - RP Bleed
 - Pseudo Aneurysm/hematoma
- Conduit Vessel Complications
- Crossing /wire related perforations
- Treatment related complications
 - Perforation
 - Embolization
- Thrombotic complications
- Renal complication
- Cerebrovascular complications
- Sedation related complications
- Cardiac Complications







Avoidance

Appropriate Procedure

- **Appropriate Patient** Pat
- By the Op
- **Appropriate Physician** Pro
 - At the
- Kn **Appropriate Site of service**
- Rei
- Just because we can do it is not an indication





Management

- Early Recognition
- Low threshold for central large bore Venous line early
- Document imagery where applicable
- Maintain calm but act decisively and promptly
- Have readily available tools on the shelf to fix it if you break it
 - Covered stents
 - Coils
 - Reversal agents for sedatives and heparin
 - Pressors
- Call for help
- It is preferable to fix the problem in the lab before you transfer if at all possible, especially when ongoing.







Management

- Focus on the patient not lawyer.
- Remember to keep talking to the patient in calm reassuring tone
- After stabilizing the patient, explain to patient & family in clear honest terms what happened.
- If a Hospital transfer was needed, have a very low threshold for accompanying the pt in the ambulance to the ER.

- USG always
- Micro Needle/Kit Always
- Aim at entring the vessel at the center of the front wall
- Puncture must be where the vessel posterior wall is supported by bone

- Femoral access must be done with a set protocol with zero tolerance for deviation.
 - **USG** always
 - Micro Needle/Kit Always
 - Fluoro confirmation of the micro needle position in the CFA to further verify.
- High sticks lead to 100% RP bleed
- Low sticks increase the risk of hematoma or **PseudoAneurysms**
- Antegrade Sticks must be steep
- If Needle Tip on Fluoro is too high or low, remove, hold for 2 mins and start again.




















- Brachial Access is still indicated in aorto iliac CTO. must be done with a set protocol with zero tolerance for deviation.
 - USG <u>always</u>
 - Micro Needle/Kit Always
 - Must stick along or very slightly below the antecubital fossa line.
 - Must feel the medial and lateral humeral condyles and draw a line between and stick there.
- The brachial artery transitions medial to the bone very quickly, and if the stick is at less than 60 degrees steep, we are likely to hit the vessel where it is no longer compressible by a bone.
- Making large arm hematomas a high likelihood.








There is no bone behind the brachial artery here to support a good hold especially with the least bit of wrist pronation thus much higher risk of hematoma and Pseudo aneurysm


Very narrow zone of wide bone behind the artery RIGHT AT THE ELBOW CREASE to allow a good brachial artery hold post op

3.7 Cross Sections of the Arm and Forearm



A Cross section through the right arm

Proximal view. The location of the sectional plane is shown in C.



THE BRACHIAL ARTERY
WILL BOW DOWN UNDER
THE MANUAL HOLD WITH
NO BONE BEHIND IT
IRRESPECTIVE OF HOW
GOOD THE RN IS,
LEADING MUCH HIGHER
RISK OF HEMATOMA NO
MATTER HOW HARD WE
PUSH.

- **Pedal Access attrition is the** least written about complication, and very serious at that. Especially as primary/sole access.
- Our anecdotal experience puts it at 5% conservatively.
- Especially likely in diffusely diseased pedals engaged with >4 Fr sheath.



- **Aleternate Access**
- Mid & Distal SFA
- Profunda



Must be closed

Popliteal






Tips

- Operator must own the access start to finish
- Low Threshold for early US post procedure
- Learn and perfect Thrombin injection techniques
- Consider having preemptive protective access to verify hemostasis angiographically if it cannot be done by US.
- High index of suspicion for RP bleed in Hypotension or abdominal pain post femoral access.

Conduit Vessel Co

- Aorto Iliac injury from wire/sheath manipulati
- Always advance and reti interventional sheath over supportive wires
- And with the dilator
- Consider advancing a so same size catheter to ac the long soft dilator in difficult friction cases.



Conduit Vessel Complications

- Severe calcification or existing stents severing catheter body
- Typical Scenario is soft catheter advanced over soft wire
- Then Supportive wire exchanged
- Then the catheter displaying resistance on pull back
- Solution: rid of supportive wire and replace with soft or moderate support wire.



Wire Related Perforation

During crossing:

- Likely to be inconsequential perforation of a small branch or "parallel collateral"
- If in Doubt Coil embolize and continue the crossing effort
- In The calf BP cuff for 5 minutes at SYS BP usually suffices

After crossing from wire tip left unchecked:

- This could be problematic
- Watch for compartment Syndrome in the calf
- Watch for Renal Subcapsular or extra capsular hematoma
- We had one anecdote of intra abdominal bleeding from .14 wire tip in a distal mesenteric branch





Treatment Related Complications

Perforation

- Free wall perforation
- Atherectomy:
 - Laser
 - Hawk
 - Jetstream
- Oversized PTA.
- Usually will require covered stent placen

Embolization:

- Macro:
 - Hawk, Jetstream, some times DB or
- Micro:
 - Diamond Back, Rotoblator.
- Best treatment is avoidance
- Use filters in <u>moderate to high</u> risk settings
- Advance Laser at < 1 mm/sec religiously
- Segmental Blades down/up technique with Jetstream is helpful
- Always Treat thrombus successfully before reverting to any other modality.
- The Dippel Principle "Do Not Cut Corners"





Treatment Related Complications


Embolization:


- When retrieving filters consider using a long 5 Fr sheath not just the filter retrieving catheter.
- Consider not fully constraining the filter to reduce the risk of spilling over embolic material.
- If residual Macro emboli persist, take 4 fr long endhole catheter to the embolus and suction it out.
- If Thrombotic embolization is suspected infuse TPA and heparin for 2-4 hours and relook.
- Inject selective I.A. Nitroglycerin, many times BTK vascular spasm could look like emboli.





Treatment Related Complications





Thrombotic Complications

- Obtaining ACT every 20-30 mins is crucial
 - Especially if addressing complex anatomy
 - Or having long catheter dwell times
- Thrombus can develop on the wire
- Can build in the sheath
- Could be part of the complex occlusion







Renal Complications

- Athero Embolization
- Contrast induced nephropathy
- Hemoglobinuria Induced ATN (with Angiojet)
- Prevention:
 - Use only 4 Fr diagnostic catheters
 - Use soft technique
 - Hold ACE, ARB, Diuretics 24-48 hours ahead
 - Hydrate, pre, in, and post procedure
 - In Procedure planning define your contrast maximum load and announce that to the team at time out.
 - Use more CO2 imaging
 - Use IVUS
 - Alkalinize the urine to prevent Hemoglobinuria and potential irreversible Tubular injury
 - Avoid exceeding 300-500cc Angiojet
 - Go to definitive treatments that require less "relook angios during the procedure"
 - Abort further attempts once contrast max given
 - Stage
 - Use IVUS





- Cerebrovascular Complications
- Arch catheter manipulation (with radial access or heart cath)
- Aortic valve crossing especially in AS cases.
- Excessive anticoagulation in setting of HTN



Sedation Related Complications

Hypoxia

- Use Music to reduce the need for sedation
- Interactive patient engagement
- Avoid Blind oxygen administration, could be deleterious in Co2 retainers (there are many of them around) once subjected to sedation in reducing resp drive.
- Have reversal agents readily available
- Correct possible airway issues before Oxygenation.

Paradoxic Agitation







